1 License Activation

1.1 User Registration

Please complete user registration on the FAWEB website, (FAWEB: <u>https://www.faweb.net/en/</u>) with the correct serial number (9 digits -8 digits) that you acquired when purchased.

If you purchased the software key product, a ticket ID will be sent to your e-mail when you complete use registration on the FAWEB site. The ticket ID is required to activate the software key.

If you purchase Hardware key, Ticket ID will not be sent.



1.2 Activate the Software Key (Online)

The following shows the procedure for activating software key when a PC with DeviceXPlorer installed can connect to the Internet.

* The ticket ID is required to activate. Please complete 1.1 User Registration to acquire the ticket ID.

(1) Open the license registration web page ("License") in FAWEB. (The license registration web page: <u>http://license.faweb.net/</u>)



(2) Input the ticket ID in the "Ticket", which you acquired at user registration on the license registration page, and click "Next.

	TAREBI(HI			English	₩ 🗖	
	(Miceljii					
	Home					
	Enter your ticke	t				
	Please enter your t Ticket will be sent t	icket and click "Next". to you via email by User Registration.				
	Ticket:					
L	AAAAA-BBBBB-CCC	CC-DDDDD-EEEE				
	Next					
	© TAKEBISHI CORPO	DRATION				
	Legal Notice CodeM	eter License Central WebDepot v21.04	309.503.ws4			

(3) Confirm that the ticket ID is correctly filled, and click "Activate Licenses".

ainer Status
Available

(4) Click "Activate License on This PC".

🍸 ТАКЕВІЗНІ				English	* 💌
Home My Licenses					
Activable license					
If the PC on which you want "Activate License on This PC	to activate the license is "; if it is a different PC,	s the same as the PC on which you a please click "Activate License on And	re operating this other PC".	s web page, please	e click
Name	Ticket	t	Activated On	CmContainer	Status
Z Takebishi Product CmActl	License Item AAAAA	A-BBBBB-CCCCC-DDDDD-EEEEE			Available
Back Activate Lice	ense on This PC	Activate License on Another PC			
My Licenses					
© TAKEBISHI CORPORATION					

(5) The following screen is displayed when process is completed.When the message "License transfer completed successfully!" is displayed, Software Key Activation is complete.

Online License Transfer
Starting license transfer. Creating license request. Downloading license update. Importing license update to CmContainer. Creating receipt. Uploading receipt.
License transfer completed successfully!
ОК

1.3 Activate the Software Key (Offline)

The following shows the Software Key Activation procedure when a PC on which DeviceXPlorer is installed cannot connect to the Internet.

* Use a PC that can access the Internet (hereinafter referred to as an Online PC) to activate a license for a PC (hereinafter referred to as an Offline PC) that has a DeviceXPlorer that cannot access the Internet.

* The ticket ID is required to activate. Please complete 1.1 User Registration to acquire the ticket ID.



If Offline Activation Tool is already installed, please refer to

"1.3.1 When using Offline Activation Tool".

If Offline Activation Tool is not installed, please refer to

"1.3.2 When not using Offline Activation Tool".

Note

Offline Activation Tool will be stored in the following path after installing this product version 7.3.0.1 or later. [Installation Directory]¥Option¥SWkeyOfflineActivation¥SWKeyOfflineActivationTool.exe

1.3.1 When using Offline Activation Tool

(1) Launch "SWKey Offline Activation Tool" from the start menu and click "License Activation".



(2) Specify the output destination of Request File and click "Export".



(3) Move "License Request File" exported in (2) to any folder on Online PC.



(4) Open the license registration web page("License") in FAWEB on the Online PC. ("License" in FAWEB : <u>http://license.faweb.net/index.php</u>)

Online PC				
			Company Inform	nation Login/Create My Account
😣 FAWEB 🏹	такеві∫ні	Luser Registration (Product Re	gistration)	Contact JA EN Q-
Products	Use Cases	Download	Support	FAQ
		2 🦴		
and the second process of the second proces of the second proces of the second process o				
ke your factory				

(5) Enter Ticket ID obtained during user registration into "Ticket:" on License Activation page, and click "Next".

	C	Inline PC		
↑ ТАКЕВІ∫НІ			English	¥ ▼
Home				
Enter your ticke	it			
Please enter your Ticket will be sent	ticket and click "Next". to you via email by User Registration.			
Ticket AAAAA-BBBBB-CCC	CCC-DDDDD-EEEE			
Next				
© TAKEBISHI CORP	ORATION			
Legal Notice CodeN	Neter License Central WebDepot v21.0	14.309.503.ws4		

(6) Check whether Ticket ID is correct and click "Activate Licenses".

	Online PC			
👕 такевіўні			English	*
Home My Licenses				
My Licenses				
Name	Ticket	Activated On	CmContainer	Status
Name Takebishi Product CmActLicense Item	Ticket AAAAA-BBBBB-CCCCC-DDDDD-EEEE	Activated On E	CmContainer	Status Available
Name Takebishi Product CmActLicense Item Back Activate Licenses	Ticket AAAAA-BBBBB-CCCCC-DDDDD-EEEEE	Activated On E	CmContainer	Status Available
Name Takebishi Product CmActLicense Item Back Activate Licenses © TAKEBISHI CORPORATION	Ticket	Activated On	CmContainer	Status Available

(7) Click "Activate License On Another PC".

	Online PC			
❤ ТАКЕВІ∫НІ			English	
Home My Licenses				
Activable license				
If the PC on which you want to activate "Activate License on This PC"; if it is a c	the license is the same as the PC on whic different PC, please click "Activate License Ticket	h you are operating this on Another PC". Activated On	web page, please CmContainer	e click Status
If the PC on which you want to activate "Activate License on This PC"; if it is a c Vame Z Takebishi Product CmActLicense Iter	the license is the same as the PC on which ifferent PC, please click "Activate License Ticket M AAAA-BBBBBB-CCCCCC-DDDDD-	h you are operating this on Another PC". Activated On EEEEE	web page, please	e click Status Available
If the PC on which you want to activate "Activate License on This PC"; if it is a c Name Takebishi Product CmActLicense Iter Back Activate License on Th	the license is the same as the PC on which ifferent PC, please click "Activate License Ticket m AAAAA-BBBBBB-CCCCCC-DDDDD- is PC Activate License on Anothe	h you are operating this on Another PC". Activated On EEEEE ar PC	web page, please	e click Status Available
If the PC on which you want to activate "Activate License on This PC"; if it is a c Activate License on This PC "; Back Activate License on The My Licenses	the license is the same as the PC on which ifferent PC, please click "Activate License Ticket m AAAAA-BBBBBB-CCCCCC-DDDDD- is PC Activate License on Anothe	h you are operating this on Another PC". Activated On EEEEE ar PC	web page, please	e click Status Available

(8) Select "License Request File" moved in (2) from "Choose File" and click "Next".

	Online PC			
👕 TAREBIŞHI			English	88 💌
Home My Licenses				
Jpload License Request File				
Upload Request File(*.WibuCmRaC	Download Update File(*.WibuCmRaU)) Com	plete(Move to off	line PC)
To activate the license on another PC 1. Start Offline Activation Tool (included operate (If you do not have Offline Activation 2. Select License Request file that you	- "Upload License Request File": I with the product) from the PC to be activated and Tool, please refer to here for instructions.) moved to this PC and click "Next".	create License F	Request file. How	to
✓ Name	Ticket	Activated On	CmContainer	Status
Takebishi Product CmActLicense Iter	M AAAAA-BBBBB-CCCCC-DDDDD-EEEEE			Available
tick a license request file (*.WibuCmRa Choose File Back Next	(C)			

(9) Click "Download License Update File Now".

		Online PC				
↑ такеві(ні				Eng	lish	₩ 💌
Home My Licenses					Operation N	lanual
Download License Upda	te File					
Upload Request File(*.Wib	uCmRaC) √	Download Update File	(*.WibuCmRaU)	Complet	e(Move to offline	PC)
"Download License Update	File":					
Click "Download License Upd	ate File Now" and sav	ve the file on your PC, the	en click "Next".			
Download License Update F	ile Now Ne:	xt				
My Licenses						

Click "Next" to display the completion screen. That's all for online PC operations.

TAH	евіўні	English 🚟 [
Home	My Licenses	Operation Manua
omplet	e(Move to offline PC)	sta Eile/t WikuCmDal I). / Complete/Meure to offline DC)
opioa		Complete(Move to Online PC)
That's a license.	II for the operations on this PC. Next, perform the follow :	wing operations on the PC where you want to activate the
1. Move	License Update file you created to the PC where you want t	to update the license.
2. Pleas	e import License Update file from Offline Activation Tool(inclu u do not have Offline Activation Tool, please refer to here for	luded with the product). How to operate r instructions.)
(If you		

(10) Copy downloaded "License Update File" to any location on Offline PC.



(11) Select the path of "Update File" created in (10) and click "Activate License".



(12) Software key activation is complete.

Offline PC
License Activation X
License Activation was successful.
ОК

1.3.2 When not using Offline Activation Tool

(1) Place the "License Request File Template File" stored on the installation disc (Option¥SWkeyOfflineActivation) or in the installation directory of the DeviceXPlorer (Option¥SWkeyOfflineActivation¥) in the any location on the offline PC.

Installation directory:

 $\label{eq:c:program} C: \eqref{eq:constraint} Program Files \eqref{eq:constraint} TAKEBISHI \eqref{eq:constraint} Device \eqref{eq:constraint} Program Files \eqref{eq:constraint} Program \eqref{eq:constraint} Progr$

C:\Program Files (x86)\TAKEBISHI\DeviceXPlorer OPC Server 7\DeviceXPlorer O

Offline PC									
^ N	lame								
	clrcompression.dll								
E	🗟 clrjit.dll								
	🗟 coreclr.dll								
	D3DCompiler_47_cor3.dll								
	🔮 mscordaccore.dll								
	PenImc_cor3.dll								
	PresentationNative_cor3.dll								
	SWKeyOfflineActivationTool.exe								
	Template_6001002_2004.WibuCmLIF								
	vcruntime140_cor3.dll								
	e wpfgfx_cor3.dll								

(2) On the offline PC, start the "CodeMeter Control Center" from the Start menu or the following path.
 CodeMeter Control Center File path to store;

 $C: \cite{Program Files} (x86) \cite{CodeMeter} \cite{Runtime} \cite{Fine} \cite{Fine} \cite{CodeMeter} \ci$



(3) Open CodeMeter Control Center, and Copy & Drop the "License Request File template" on "License" of CodeMeter Control Center.



(4) After placing "License Request File template", "Empty License Container" is displayed on "License" in CodeMeter Control Center. Select the added license container and click "Update License".



(5) Click "Next.>" button.



(6) Check "Create license request" and click "Next".



(7) Save the created "License Request File " in any folder, specify the save folder to save and click "Next".



(8) "License Request File" is created, the following screen is displayed. Click "Finish".



(9) Transfer the "License Request File" that created in Offline PC to any folder on the Online PC.



(10) Open the license registration web page("License") in FAWEB on the Online PC. ("License" in FAWEB : <u>http://license.faweb.net/index.php</u>)

		Online PC		
			Company Infor	mation Login/Create My Account
🍀 FAWEB 🌱	такеві{ні	Luser Registration (Product R	egistration)	Sontact JA EN Q.
Products	Use Cases	Download	Support	FAQ
ke your factory				

(11) Enter Ticket ID obtained during user registration into "Ticket:" on License Activation page, and click "Next".

Online PC							
🔭 ТАКЕВІЗНІ	English	※ 🗹					
Home							
Enter your ticket							
Please enter your ticket and click "Next". Ticket will be sent to you via email by User Registration.							
Ticket AAAAA-BBBBBB-CCCCCC-DDDDD-EEEE							
© TAKEBISHI CORPORATION							
Legal Notice CodeMeter License Central WebDepot v21.04.309.503.ws4							

(12) Check whether Ticket ID is correct and click "Activate Licenses".

	Online PC			
∼ такеві(ні			English	※ 🗹
Home My Licenses				
My Licenses				
My Licenses	Ticket /	Activated On	CmContainer	Status
My Licenses Name Takebishi Product CmActLicense Item	Ticket AAAAA-BBBBB-CCCCC-DDDDD-EEEEE	Activated On	CmContainer	Status Available
My Licenses Name Takebishi Product CmActLicense Item Back Activate Licenses	Ticket AAAAA-BBBBBB-CCCCC-DDDDD-EEEEE	Activated On	CmContainer	Status Available

(13) Click "Activate License On Another PC".

	Online PC			
₹ ТАНЕВІ(НІ			English	* 🗷
Home My Licenses				
Activable license				
If the PC on which you want to activate	the license is the same as the PC on which you	are operating this	web page, please	e click
If the PC on which you want to activate "Activate License on This PC"; if it is a	the license is the same as the PC on which you different PC, please click "Activate License on Ar Ticket	are operating this nother PC".	web page, please CmContainer	e click Status
If the PC on which you want to activate "Activate License on This PC"; if it is a Name Takebishi Product CmActLicense Ite	the license is the same as the PC on which you different PC, please click "Activate License on Ar Ticket m AAAAA-BBBBBB-CCCCCC-DDDDD-EEEE	are operating this nother PC". Activated On	web page, please	e click Status Available
If the PC on which you want to activate "Activate License on This PC"; if it is a Name Takebishi Product CmActLicense Ite Back Activate License on Ti	the license is the same as the PC on which you different PC, please click "Activate License on Ar Ticket m AAAAA-BBBBB-CCCCCC-DDDDD-EEEE his PC Activate License on Another PC	are operating this other PC". Activated On E	web page, please	e click Status Available
If the PC on which you want to activate "Activate License on This PC"; if it is a Name Takebishi Product CmActLicense Ite Back Activate License on TT My Licenses	the license is the same as the PC on which you different PC, please click "Activate License on Ar Ticket m AAAAA-BBBBBB-CCCCCC-DDDDD-EEEE his PC Activate License on Another PC	are operating this nother PC". Activated On E	web page, please	e click Status Available

(14) Select "License Request File" moved in (2) from "Choose File" and click "Next".

	Online PC			
∼ таневі§ні			English	*
Home My Licenses				
Upload License Request File	Download Lindato Eilo(*1Mihu/CmDat	D Cor	malata/Mayo to off	Ring PC)
To activate the license on another PC - "	Upload License Request File":			
 Start Offline Activation Tool (included wit operate (If you do not have Offline Activation Too Select License Request file that you move 	h the product) from the PC to be activated and I, please refer to here for instructions.) red to this PC and click "Next".	I create License	Request file. How	to
✓ Name	Ticket	Activated On	CmContainer	Status
Takebishi Product CmActLicense Item	AAAAA-BBBBB-CCCCC-DDDDD-EEEEE			Available
Pick a license request file (*.WibuCmRaC) Choose File No file chosen				

(15) Click "Download License Update File Now".

	Online PC	
∼ такеві{ні		English 😹 💌
Home My Licenses		Operation Manual
Download License Update File	e	
Upload Request File(*.WibuCmRa	aC) ✓ Download Update File(*.WibuCmRaU	Complete(Move to offline PC)
"Download License Update File":		
Click "Download License Update File	e Now" and save the file on your PC, then click "Next".	
Download License Update File Now	v Next	
2		

Click "Next" to display the completion screen. That's all for online PC operations.

			Onli	ne PC				
TAP	еві∫ні					Englis	h	₩
Home	My License	s				Ĩ	Operation I	Manual
Complet	e(Move to of	ffline PC)						
Dates			No. of the second second			A. 15	Name of the State	
Upioa	d Request File(*	WibuCmRaC) √	Download Up	date File(*.WibuCn	nRaU)√	Complete(Move to offlin	e PC)
That's a license	d Request File(* Ill for the operat	WibuCmRaC) ✓	Download Up ext, perform the foll	date File(*.WibuCn	nRaU) √ s on the PC w	Complete(Move to offlin t to activate t	e PC) he
That's a license. 1. Move 2. Pleas (If yo	d Request File(* ill for the operat : License Update be import License u do not have Of	WibuCmRaC) √ tions on this PC. N file you created to to b Update file from O fline Activation Tool,	Download Up ext, perform the foll he PC where you wa ffline Activation Tool(i please refer to here	date File(*.WibuCn lowing operations ant to update the lic included with the pr for instructions.)	nRaU) √ s on the PC w cense. roduct). How to	Complete(here you want	Move to offlin t to activate t	he

(16) Copy downloaded "License Update File" to any location on Offline PC.

Online PC		Offline PC
	ٽ ~	SWKeyOfflineActivationTool ✓ Ö
▲ Name		^ Name ^
130-xxxxxxxx.WibuCmRaC		130-xxxxxxxx.WibuCmRaC
Update_130-xxxxxxxxWibuCmRaU		Update_130-xxxxxxx.WibuCmRaU

(17) Start CodeMeter Control Center on an Offline PC. Select the license that is "Empty license container" and Click "License Update".

	C	Offline PC	
	S CodeMeter Control Center	_	o x
	File Process View Help		
	License Events		_
	Takebishi CmActLicense 60010 130-2596107912	Name: Takebishi CmActLicense 6001002	
		Serial: 130-2596107912	
		Version: CmActLicense 3.00	
		Status: 🛞 Empty license container	
		License Update Remove License	
	CodeMeter service is running.	[WebAdmin
(18)	Check "Import license	update" and click "Next".	
· -/	(Offline PC	
	-	?	×
	← 🕞 CmFAS Assistant		
	Please select the desired ac	tion	
	○ Create license request		
	Choose this option if you want to co software.	reate a license request file in order to send it to the vendo	r of the
	Import license update		
	Choose this option, if you received import this file.	a license update file from the software vendor and want t	20
	Create receipt		
	software vendor.	onnirm the successful import of a license update file for the	

(19) Select "License Update File" saved in Offline PC and click "Commit".

Offline PC						
	?	×				
← ⓒ CmFAS Assistant						
Please select the file name						
C:/Users/seigi/Documents/130-2596107912.WibuCmRaU						
Select a file under which the license update file is stored on your computer. Then dick on 'co import the new licenses.	nmiť to	,				
Commit	Help	•				

(20) Software key activation is complete. *Uploading Receipt File is no longer required.

Offline PC							
CodeMete	r	?	×				
i	Informat Import Up	ion: odate succ	essful.				
		O	K				

1.4 Deactivate the Software Key (Online)

(1) Open the license registration web page ("License" <u>http://license.faweb.net/index.php</u>) in FAWEB.



(2) Input the ticket ID in the "Ticket:", which you acquired at user registration on the license registration page, and click "Next. (Ticket ID linked to product serial number.)

∼ такеві\ні			English	
Home				
Enter your ticket				
Please enter your ticket and click "Nex Ticket will be sent to you via email by l	t". Jser Registration.			
Ticket AAAAA-BBBBBB-CCCCC-DDDDD-EEEEF	:			
Next				
© TAKEBISHI CORPORATION				
Legal Notice CodeMeter License Centra	I WebDepot v21.04.309.503.ws4	4		

(3) Click "Deactivate Licenses".

💙 ТАКЕВІ(НІ			E	nglish 🏼 🎛 💌
Home My Licens	ses			Operation Manual
ly Licenses				
Name	Ticket	Activated On	CmContainer	Status
Takebishi Product	AAAAA-BBBBBB-CCCCC-	2024-01-09	• 130 - xxxxxxxxx	Activated

(4) Click "Deactivate License on This PC".

∼ такеві{ні			English	*
Home My Licenses			Operatio	on Manual
Deactivable Licenses				
If the PC on which you want to deac "Deactivate License on This PC"; if i	tivate the license is the same as the PC t is a different PC, please click "Deactiv	C on which you are opera rate License on Another	ating this web page, plea PC".	ise click
✓ Name	Ticket	Activated On	CmContainer	Status
 Name Takebishi Product CmActLicense Item 	Ticket AAAAA-BBBBBB-CCCCC- DDDDD-EEEE	Activated On 2024-01-09 12:22:45	CmContainer 130 – xxxxxxxxx (Machine name)	Status Activated
Name Takebishi Product CmActLicense Item Back Deactivate License	Ticket AAAAA-BBBBBB-CCCCC- DDDDD-EEEEE on This PC Deactivate Licen	Activated On 2024-01-09 12:22:45 se on Another PC	CmContainer 130 – xxxxxxxxx (Machine name)	Status Activated

(5) The following screen is displayed when process is completed.When the message "License transfer completed successfully!" is displayed, Software Key Activation is complete.

Online License Update
Starting license update. Creating license request. Downloading license update. Importing license update to CmContainer. Creating receipt. Uploading receipt.
License update completed successfully!
ОК

1.5 Deactivate the Software Key (Offline)

The following shows the procedure for deactivate the software key when the PC on which DeviceXPlorer is installed cannot connect to the Internet.

* Use a PC that can access the Internet (hereinafter referred to as Online PC) to transfer the software key of the PC (hereinafter referred to as Offline PC) where DeviceXPlorer that cannot access the Internet is installed.



If Offline Activation Tool is already installed, please refer to

"1.5.1 When using Offline Activation Tool".

If Offline Activation Tool is not installed, please refer to

"1.5.2 When not using Offline Activation Tool".

Note

Offline Activation Tool will be stored in the following path after installing this product version 7.3.0.1 or later. [Installation Directory]¥Option¥SWkeyOfflineActivation¥SWKeyOfflineActivationTool.exe

1.5.1 When using Offline Activation Tool

Open the license registration web page ("License") in FAWEB.
 (The license registration web page: <u>http://license.faweb.net/index.php</u>)



(2) Input the ticket ID got at the time of user registration, and click "Next". (Ticket ID linked to product serial number is issued.)

Online PC		
такеві∫ні	English	*
Home		
Enter your ticket		
Please enter your ticket and click "Next". Ticket will be sent to you via email by User Registration.		
Ticket: AAAAA-BBBBBB-CCCCCC-DDDDD-EEEEE		
© TAKEBISHI CORPORATION		
Legal Notice CodeMeter License Central WebDepot v21 04 309 503 ws4		

(3) Click "Deactivate Licenses".

		Engl	sh 💥 💌
			Operation Manual
Ticket	Activated On	CmContainer	Status
AAAAA-BBBBBB-CCCCC- DDDDD-EEEEE	2024-01-09 12:22:45	 130 – xxxxxxxxxx (Machine name) 	Activated
	Ticket AAAAA-BBBBB-CCCCC- DDDDD-EEEEE	Ticket Activated On AAAAA-BBBBB-CCCCC- 2024-01-09 DDDDD-EEEEE 12:22:45	Ticket Activated On CmContainer AAAAA-BBBBBB-CCCCCC- 2024-01-09 • 130 – xxxxxxxxx DDDDD-EEEEE 12:22:45 (Machine name)

(4) Click "Deactivate License on Another PC".

	Online PO	C		
∼ такеві5ні			English	*
Home My Licenses			Operatio	n Manual
Deactivable Licenses				
If the PC on which you want to deactive "Deactivate License on This PC"; if it is	ate the license is the same as the PG a different PC, please click "Deactiv	C on which you are opera vate License on Another	ating this web page, plea PC".	se click
✓ Name	Ticket	Activated On	CmContainer	Status
Takebishi Product CmActLicense Item	AAAAA-BBBBB-CCCCC- DDDDD-EEEEE	2024-01-09 12:22:45	130 – xxxxxxxxx (Machine name)	Activated
				, ion rated
Back Deactivate License on	This PC Deactivate Licen	nse on Another PC		

(5) Download Update File from "Download License Update File Now" and click "Next".

Online PC				
👕 ТАНЕВІЗНІ	English 🚟 💌			
Home My Licenses	Operation Manual			
Download License Update File				
Download Update File(*.WibuCmRaU)	Upload Receipt File			
"Download License Update File": Click "Download License Update File Now" and save the file on your PC,then click "Next".				
Back Download License Update File Now Next				
My Licenses				

(6) Move downloaded "License Update File" to any folder on Offline PC.

Online PC		Offline PC
	5 V	SWKeyOfflineActivationTool → Č
^ Name		^ Name
Update_130-xxxxxxx.WibuCmRaU	_	Update_130-xxxxxxx.WibuCmRaU

(7) Launch "SWKey Offline Activation Tool" from the start menu and click "License Deactivation".



(8) Specify Update file moved in (6) and click "Export".

	Offline PC
SWKey Offline Activation Tool	- 🗆 X
	Obtain Update File (on the PC connected to the internet) Input the URL below into your browser.
License Activation	http://license.taweb.net/index.php?lang=en Copy After entering Ticket ID on Webpage, obtain Update File.
C License Deactivation	
	 Create Receipt File (on this PC) Select Update File obtained in ① and export Receipt File. Update File Path C#Users#ysugle#Documents#TAKE8ISHI#SWKeyOfflineActiva Export Receipt File to a different folder than Update File Export Upload Receipt File (on the PC connected to the internet) Please upload Receipt File from ② on the web page ③.

(9) Move "Receipt File" created in (8) to any folder on Online PC.



(10) Select Receipt File moved in (9) and click "Upload Receipt File Now".

		Online PC			
☆ tarebishi			E	nglish	*
Home My Li	censes			Operation	Manual
Complete(Move	to offline PC)				
	Download Update File(*.)	NibuCmRaU)	Upload	t Receipt File	
 Please import I (If you do not h Select Receipt You can download 	icense Update file and get Re ave Offline Activation Tool, ple File you moved to this PC, Clic I license update file again. Clic	ceipt File from Offline Activation 1 ase refer to here for instructions.) ck "Upload Receipt Now". :k "Back" to get to the download p	Tool(included with the produ) page.	ct). How to opera	ite
Pick license receipt Choose File No file	file (*.WibuCmRaC) e chosen				
Back U	pload Receipt File Now				
My Licenses					

(11) The following screen is displayed and license deactivation is complete.

Online PC				
🍸 ТАКЕВІ(НІ	English	** 💌		
Home My Licenses	Operatio	on Manual		
License Update Successfully Completed				
The license Update has been completed successfully.				
ОК				

1.5.2 When not using Offline Activation Tool

Open the license registration web page ("License") in FAWEB.
 (The license registration web page: <u>http://license.faweb.net/index.php</u>)

		Online PC		
			Company Inform	ation Login/Create My Account
😣 FAWEB 🏹	такевісні	Luser Registration (Product Re	egistration)	Contact JA EN Q-
Products	Use Cases	Download	Support	FAQ
	and a second			
ke your factory		*		

(2) Input the ticket ID got at the time of user registration, and click "Next". (Ticket ID linked to product serial number is issued.)

Online PC						
γ ТАКЕВІ́НІ	English	1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1				
Home						
Enter your ticket						
Please enter your ticket and click "Next". Ticket will be sent to you via email by User Registration.						
Ticket						
© TAKEBISHI CORPORATION						
Legal Notice CodeMeter License Central WebDepot v21.04.309.503 ws4						

(3) Click "Deactivate Licenses".

TAUERI(MI				
INKEDISHI			Engli	sh 🏽 🎛 💌
Home My Licenses				Operation Manual
My Licenses				
Name	Ticket	Activated On	CmContainer	Status
Takebishi Product CmActLicense Item	AAAAA-BBBBBB-CCCCC- DDDDD-EEEEE	2024-01-09 12:22:45	 130 – xxxxxxxxxx (Machine name) 	Activated

(4) Click "Deactivate License on Another PC".

		Online P	C		
7	такевізні			English	₩
н	ome My Licenses			Operatio	n Manual
Dea	activable Licenses				
lf "C	the PC on which you want to deact Deactivate License on This PC", if it Name	ivate the license is the same as the P is a different PC, please click "Deacti Ticket	C on which you are opera vate License on Another Activated On	ating this web page, plea PC". CmContainer	se click Status
	Takebishi Product CmActLicense Item	AAAAA-BBBBB-CCCCC- DDDDD-EEEEE	2024-01-09 12:22:45	130 – xxxxxxxxxx (Machine name)	Activated
	Back Deactivate License	on This PC Deactivate Licer	nse on Another PC		
	ly Licenses				

(5) Download Update File from "Download License Update File Now" and click "Next".

Online PC								
∼ такеві∫ні	English 😹 💌							
Home My Licenses	Operation Manual							
Download License Update File								
Download Update File(*.WibuCmRaU)	Upload Receipt File							
"Download License Update File": Click "Download License Update File Now" and save the file on your PC, then click "Next".								
Back Download License Update File Now Next								
My Licenses								

(6) Move downloaded "License Update File" to any folder on Offline PC.

Online PC		Offline PC
> PC > OS (C:) > temp	ٽ ~	► PC > OS (C:) > temp v ੋ
▲ Name		^ Name ^
Update_130-xxxxxxx.WibuCmRaU		Update_130-xxxxxxxWibuCmRaU

(7) Start "CodeMeter Control Center" from the start menu. Select the license you want to deactivate and click "Update License".



(8) Check "Import license update" and click "Next".



(9) Select "License Update File" saved in Offline PC and click "Commit".



(10) Create a receipt file from "here" on this screen.

Offline PC		
	?	×
← ⓒ CmFAS Assistant		
The license update has been successfully imported.		
You will find details for the imported licenses in the CodeMeter WebAdmin. In order to for the vendor please clicence.	create a re	ceipt
Finish	н	elp

(11) Specify where to save of the created receipt file in any folder on the Offline PC and click "Commit".



(12) When the created license file is saved, the following screen is displayed.



(13) Move "Receipt File" created in (12) to any folder on Online PC.



(14) Select Receipt File moved in (13) and click "Upload Receipt File Now".

		Online PC		
₩ TAREBISH	1		E	English 🗰 🖼
Home My L	icenses			Operation Manual
Complete(Mov	e to offline PC)			10
"Upload Receip	t File":			
1. Move License 2. Please import (If you do not	Update file you created t License Update file and have Offline Activation To	o the PC where you want to deactival get Receipt File from Offline Activation ol, please refer to here for instruction:	te the license. n Tool(included with the prod s.)	luct). How to operate
3. Select Receip You can downloa	t File you moved to this P ad license update file agai	C, Click "Upload Receipt Now".	i page.	
Pick license receip	ot file (*.WibuCmRaC)			
Choose File No fi	lle chosen			
Баск	Upload Receipt File Now			
My Licenses				

(15) The following screen is displayed and license cancellation is complete.

	Online PC					
	(* такевіўні	English 🗱 💌				
1	Home My Licenses	Operation Manual				
L	License Update Successfully Completed					
	The license Update has been completed successfully.					
	OK					